


Sonicwall

UDP-Session Timeout setzen v5.9:

Step 1: Log into the SonicWall firewall.

Step 2: Go to Firewall Settings | Advanced.

Step 3: Scroll down to the section called UDP.



Step 4: Modify the default UDP Connection Timeout, to the desired value.


Please, be aware that this modification will only apply to new connections (firewall rules, etc).

UDP-Session Timeout setzen v6.5:

SonicOS 6.5 was released September 2017. This release includes significant user interface changes and many new features that are different from the SonicOS 6.2 and earlier firmware. The below resolution is for customers using SonicOS 6.5 and later firmware.

Log into the SonicWall firewall.

1. Click **Manage** in the top navigation menu
2. Go to **Firewall Settings | Flood Protection**.
3. Click on **UDP** Tab.
4. Under **UDP Settings**
5. Modify the default **UDP Connection Timeout**, to the desired value.
6. Click on **Accept** to save the changes



Please, be aware that this modification will only apply to new connections (firewall rules, etc).